

Permission Manager

User Guide

Copyright

Copyright ©2008-2017 BoostSolutions Co., Ltd. All rights reserved.

All materials contained in this publication are protected by Copyright Law and no part of this publication may be reproduced, modified, displayed, stored in a retrieval system, or transmitted in any form or by any means, electronic, mechanical, photocopying, recording or otherwise, without the prior written consent of BoostSolutions.

Our web site: http://www.boostsolutions.com/

Contents

١.	Prod	duct introduction	I
2.	Syst	em Requirements	2
	2.1	Operating System	2
	2.2	SQL Server	2
	2.3	SharePoint Versions	2
	2.4	Browser Clients	2
3.	Lice	nsing	4
4.	Inte	rface Introduce	6
	4.1	Navigation pane	6
	4.2	Contents area	7
	4.3	lcons	8
5.	Finc	an item in content table	10
	5.1	Search	10
	5.2	Sort	10
	5.3	Paging	11
6.	Mar	nage Permissions	12
	6.1	Entering Permission Manager	12
	6.2	Grant Permissions	12
	6.3	Edit User Permissions	14
	6.4	Delete Permissions	15
	6.5	Remove User Permissions	17
	6.6	Clone Permissions	18
	6.7	Clean Dead Users	20
	6.8	Export Permissions	22
	6.9	Import Permissions	23
	6.10	Change Inheritance	25
	6.11	View SharePoint Groups	26
7.	Sea	ch Permissions	29
	7.1	Search Account Permission	29
	7.2	Export to Excel	30

7.3	Manage permissions based on search results	31
8. Man	age Users and Groups	35
8.1	View all SharePoint groups	35
8.2	Create SharePoint group	37
8.3	Edit SharePoint group	37
8.4	Delete SharePoint group	38
8.5	Export SharePoint groups	39
8.6	Add Users in group	39
8.7	Copy/Move Users to SharePoint groups	40
8.8	Delete group members	41
8.9	Delete users from site collection	42
8.10	Export SharePoint users	43
8.11	Delete domain groups	43
8.12	View Group members	45
8.13	Export all domain groups	45
9. Man	age Column & View Permission	47
9.1	Manage Column Permission	47
9.1.1	Entering column permission	47
9.1.2	Enable/Disable column permission	48
9.1.3	Activate/Deactivate permission part	48
9.1.4	Add a permission part	49
9.1.5	Edit permission part	50
9.1.6	Delete permission part	50
9.1.7	Export/Import permission settings	50
9.1.8	Advanced Settings	52
9.2	Manage View Permission	52
9.2.1	Entering view permission	52
9.2.2	Enable/Disable view permission	53
9.2.3	Activate/Deactivate permission part	53
9.2.4	Add a permission part	54
9.2.5	Edit permission part	55
9.2.6	Delete permission part	55

9.2.7	7 Export/Import permission settings	56
9.2.8		
10. N	lanage Account	58
10.1	Add Account	58
10.2	Delete Account	58
11. Lo	ogs	60
11.1	View details	60
11.2	Delete logs	61

1. Introduction

Permission Manager provides a centralized platform to manage permissions. Administrator can search, analyze, and manage SharePoint users or group permissions as well as add, modify and remove permissions on different levels, web applications, sites, lists and items.

Also, administrator can manage SharePoint group on the platform, include create, edit and delete groups; add, copy/move and remove members.

This user guide is intended to walk you through the process of how to work with BoostSolutions Permission Manager.

For latest version of this copy or other user guides, please visit our document center:

http://www.boostsolutions.com/download-documentation.html



2. System Requirements

Permission Manager 2.0 can be used on the following platforms and browsers which have been installed and deployed on SharePoint.

2.1 Operating System

- Windows Server 2008 (x86 and x64)
- Windows Server 2008 R2 (x86 and x64)
- Microsoft Windows Server 2012 Standard or Datacenter X64
- Microsoft Windows Server 2016

2.2 SQL Server

- SQL Server 2008 (x86 and x64)
- SQL Server 2008 R2 (x86 and x64)
- SQL Server 2012
- SQL Server 2014
- SQL Server 2016

2.3 SharePoint Versions

- Microsoft SharePoint Foundation 2010
- Microsoft SharePoint Server 2010
- Microsoft SharePoint Foundation 2013
- Microsoft SharePoint Server 2013
- Microsoft SharePoint Server 2016

2.4 Browser Clients

- Microsoft Internet Explorer 8.x and above (recommended for Advanced Administration features)
- Google Chrome



Mozilla Firefox



3. Licensing


Permission Manager has a 30 day trial periods. There are no functional limitations during the trial period. After 30 days, starting from the time of installation, the trial version will expire and Permission Manager will stop working.

To purchase a license, you need to visit the BoostSolutions web site at:

http://www.boostsolutions.com/purchase.html

Once you have purchased a license, you will need to enter it into the SharePoint farm. The following steps will show you how to register your license.

a. Click Settings > License Management.




b. In the License Management page, click Register.

Manage License		
Farm ID:	(JEL-700-JL 20-E 4-0702 425-J-26-5-JL)	
rarm ID:	{dfb790db-38af-4c97-ae82-436dc3fc6cdb}	
Number of servers in Farm:	1	
Version:	2.0.325.0	
License Type:	Farm Scale	
Expiration Date:	Never	
Premium Support (Expiration Date):	N/A	
License Server Amount:	1	
License Category:	Regular	
Purchase link:	Click here to purchase license	
License Registration:	Register	



c. In the **Register or Upgrade License** window, upload the license code file or enter the license code and click the **Register** button.






4. Interface Introduce

The application consists of two primary panes: Navigation pane and contents area.

There are four buttons present the Permission Manager main functional areas: Permission Management, Permission Search, User and Group Management, and Column/View Permission (this menu will be shown depend on if the Column/View Permission installed on your SharePoint server).


The Content area contains a variety of screens that provide detailed information regarding the object selected in the Navigation pane.



4.1 Navigation pane

Under each button of the navigation pane, there is farm tree which is auto-generated based on SharePoint environment and provides different hierarchical corresponding the button selected.







Clicking on any of the web application will trigger the application to display the site collections for that web application.

Clicking on any of the site will trigger the application to display the lists and libraries under that site.


Clicking on any of the list or library will trigger the application to display the items.

Right-click one node, you can refresh the farm tree.

4.2 Contents area

The Content area displays the different information corresponding to the object selected in the Navigation pane.





Select (or unselect) multiple items, click the check-boxes next the items.

Or, you can select them by following ways:

- In order to select (or unselect) multiple items, click on the first item and then holding the SHIFT key, click on the last item. All the items will be highlighted.
- In order to select (or unselect) multiple items, hold down the CTRL key and select individual files.

Select one item, then the permissions settings will be shown below the content table as following.



4.3 Icons

There are many icons in Permission Manager, here we introduce the presentation of each icon.

Icons	Descriptions
	Farm
	Web application
呂	Site which permission is unique.
&	Site which permission is inherited.
=	Sub sites
	List which permission is unique.



⊞	List which permission is inherited.
	Library which permission is unique.
	Library which permission is inherited.
	Folder which permission is unique.
	Folder which permission is inherited.
	Item which permission is unique.
	Item which permission is inherited.
Q	Refresh the content area.
C	Refresh the farm tree.



5. Find an item in content table

In a content table, administrator can quick find an item using one of following methods: filter or sort.

5.1 Search



In the **Search** box, type a few letters to narrow your search, and then click the **Search** button $^{\mathbf{Q}}$.

Note: By default, only following columns are searched for each content tables:

Site/List/Item: NameAll Users: Name

SharePoint Groups: Name


SharePoint Groups: NameDomain Groups: Name

• Group Members: Name

5.2 Sort

To sort a list of items, click a column heading. To reverse the sort order, click the column heading again.

The Ascending Sort icon - and Descending Sort icon indicate which way the list is sorted.





5.3 Paging

By default, only 20 items are displayed each page, administrator can control how many items display by clicking the specified number, 50 or 100.

To view more items, click the page number or arrows.





6. Manage Permissions

Permission Manager has an independent interface to help administrators manage permissions on one page. In this chapter, you will find information about the user interface.


6.1 Entering Permission Manager

You can open Permission Manager in 3 ways:

- a. By double clicking the **Permission Manager** shortcut on the desktop;
- b. Or by clicking **Start**, point to **All Programs** > **BoostSolutions**, and then selecting **Permission Manager**.
- c. Or, by opening a browser and entering: **http://< machine>: 8787**. If the default port number has been changed from 8787, enter the new port number.


6.2 Grant Permissions

This operation allows you to assign permissions to the user(s) or group(s). You can grant permissions or add users to SharePoint groups on multiple scopes (sites, lists or folders).





- b. Select one scope (site, list or folder) from the farm tree, and select one or more scopes (sites, lists or folders) which you want to grant user permissions.
- c. Click **Grant Permissions** on the toolbar; a dialog window will appear.




d. Enter the user or group name in the **Users/Groups** box.

Note: Domain user, group and SharePoint group are supported in this operation.

- e. Click the would button (found next to the **Users/Groups** text box), to validate the user or group.
- f. Assign permissions to the user or group in the **Grant Permissions** section.
 - Add users to the following SharePoint groups: Add domain users or groups to SharePoint groups.
 - **Give users the following permission directly**: Assign permissions to specified users or groups.






- g. Click the **Grant** button.
- h. You can confirm if permissions are broken before the operation runs. Click **OK** to run the operation immediately.

6.3 Edit User Permissions

This operation enables you to edit user(s) or group(s) permissions on one scope (sites, lists or folders).

a. Navigate to Permission Management.



b. Select one scope (site, list or folder) from the farm tree, then select a site or list which you want to edit permissions.






Select one user or group in the Permission Settings section and click Edit.



d. In the **Choose Permissions** section, specify the permissions you want the user or group to have .




- e. Click **OK**.
- f. If the scope inherits permissions from the parent, you will be warned if the permissions are broken before the operation can run, click **OK** to run the operation immediately.

6.4 Delete Permissions

This operation allows you to delete user or group permissions from the permission settings on one scope (sites, lists or folders).





b. Select one scope (site, list or folder) from the farm tree, and select a site or list.




c. In the **Permission Settings** section, select one user or group and click **Delete**.



d. Click the **OK** button.






e. If the scope inherits permissions from the parent, you will be warned if the permissions are broken before the operation can run, click **OK** to run the operation immediately.

6.5 Remove User Permissions

The **Remove User Permissions** enables you to remove user(s) or group(s) permissions or delete them from SharePoint groups.


a. Navigate to Permission Management.




b. Select one scope (site, list or folder) from the farm tree, and select sites or lists which you want to remove permissions.



c. Click **Remove User Permissions** on the toolbar and a dialog box will appear.



d. Enter the user(s) or group(s) name in the **Select Users/Groups** box.




- e. Remove user or group permissions.
 - **Remove all permission given directly**: Remove permissions from specified users or groups.
 - Remove users from all SharePoint groups: Remove users or groups from all SharePoint groups.
- f. Click the **Remove** button.

6.6 Clone Permissions

The **Permission Manage**r allows you to clone user permissions for web application level, site collection level, site level, list level and folder level.

You can copy one user's permissions and group memberships to more target users.






b. Select one scope from the farm tree, and select sites or lists which you want to clone permissions.


Note: This operation is not supported for inherited scopes.

c. Click **Clone Permissions** on the toolbar and a dialog window will appear.



d. In the **Clone permission from** box, enter the domain user(s) or group(s) name.





Note: You only need to input one user or group name.


- e. In the Clone permission to box, enter one or more domain user(s) or group(s) names.
- f. Select the permission operations by checking the check-boxes in the **Options** section.
 - Clone source user or group permissions given directly: Will only copy the given permissions to the target users or groups.
 - Add destination users/groups to source user's SharePoint groups: Will add the target users to SharePoint groups which the original user belongs to.
 - **Include unique sub sites, lists and folders**: Specify if you want to assign permissions to these contents.
- g. Click **Clone** to run the operation immediately.

6.7 Clean Dead Users


This operation allows administrators to remove disabled and non-existent domain users from a site collection.

Note: This operation is only available when you select a site collection.






- b. Select one web application from the farm tree, and select one site collection.
- c. Click **Clean Dead Users** on the toolbar and a dialog window will appear.



d. Select the status of dead users.



- Users deleted in domain: Users exist on SharePoint but have been deleted in domain.
- **Users disabled in domain**: Users exist on SharePoint but have been disabled in domain.
- e. Click the Next button.
- f. All the disabled users or non-existent users will be listed in the dialog.






Note: Dead users will be removed from site collection after you click Clean.

g. Click **Clean** to remove users from the site collection.

6.8 Export Permissions


Export Permissions enables you to export the object permission settings as an xml file as a backup or template.

a. Navigate to Permission Management.



b. Select one scope from the farm tree, and select one site or list which you want to export permission settings.






c. Click **Export Permissions** to save an xml to your local computer.




6.9 Import Permissions

This operation is used to import permission settings from an xml file.




- a. Select one scope from the farm tree, and select one or more sites or lists which you want to import permission settings from.
- b. Click **Import Permissions** on the toolbar and a dialog window will appear.






- c. Click **Browse...** to find an xml file.
- d. Select the permission operation by checking the check-box.
 - **Replace original permissions of the scopes**: Will replace all permission settings of the selected sites, lists or folders.

•



e. Click **Next** will display permission settings containing in the xml file.






f. Click **Import** to run the operation immediately.

Note: Importing permissions from different site collection is not supported.


6.10 Change Inheritance

Change Inheritance allows you to break or inherit permission settings for the selected scopes (sites, lists or folders).






- b. Select one scope from the farm tree, and select one or more lists which you want to change permissions for.
- c. Click **Change Inheritance** on the toolbar and a dialog window will appear.



d. Change inheritance by clicking the radio button.




- Break permissions: Stop inheriting permissions from the parent object.
- **Inherit permissions**: Inherit permissions from the parent object.
- e. Click **OK** to change permissions for the selected scopes.


6.11 View SharePoint Groups

This operation enables you to check SharePoint groups and members. You can also export details as an excel file.






- b. Select one site which you want to view SharePoint groups.
- c. Click SharePoint Groups on the toolbar and a dialog window will appear.



d. SharePoint groups and members will be shown in the dialog window.





e. Click **Export** to export the groups and members to an excel file.






7. Search Permissions


7.1 Search Account Permission

Search Permissions enables you to search user permissions on different levels.

a. Navigate to **Permission Search**.



- b. Select the scope from the farm tree which you want to search permissions for.
- c. Enter a user or group name in the box.




d. To select more rules, check the boxes under the text box.

Only show unique permissions: Will only search the account's permission on objects which permissions are broken.

Include account's permission on item level: Specify if the item will be shown in the search results.



e. Clicking **Search** and the search results will be show.



- f. Search results include the following columns:
 - Name: The object name, such as site, list, folder or item title.
 - Permissions: All permissions the specified account has, including permissions given directly or by groups.
 - Inherited: The permissions the object has, either inherited or unique.
 - Level: The objects level, site, list or folder.
 - Path: The site, list, folder or item location.

7.2 Export to Excel

Export to Excel enables you to export search results to an excel file.

- a. Search a user or group permissions for one scope (site, list or folder) and wait for the results to display.
- b. Click Export to Excel.



An xml file will be saved to your local computer.






7.3 Manage permissions based on search results


After searching an account's permissions, you can manage permissions including **Grant permissions**, **Remove user Permissions** and **Clone permissions**.

Grant Permissions

a. In the search results, select the site or list which you want to grant permissions.



b. Click **Grant Permissions** on the toolbar and a dialog window will appear.







- c. Assign permissions to the user(s) or group(s).
 - Add users to the following SharePoint groups: Will add the domain user(s) or group(s) to SharePoint groups.
 - **Give users the following permissions directly**: Assign permissions to the specified user(s) or group(s).
- d. Click the Grant button.

Remove User Permissions

a. In the search results, select the site or list which you want to remove user permissions.



b. Click Remove User Permissions on the toolbar and a dialog window will appear.




- c. Assign permissions to the user(s) or group(s).
 - Remove all permission given directly: Remove permissions from the specified user(s) or group(s).




- Remove users from all SharePoint groups: Remove the user(s) or group(s) from all SharePoint groups.
- d. Click the Remove button.

Clone Permissions

a. In the search results, select the site or list which you want to clone user permissions. This function is available for objects whose permission has been broken.



b. Click **Clone Permissions** on the toolbar and a dialog window will appear.





- c. Assign permissions to the user(s) or group(s).
 - Clone source user or group permissions given directly: Will only copy the given permissions to the target user(s) or group(s).
 - Add destination users/groups to source user's SharePoint groups: Will add the target user(s) to the SharePoint groups which the original user(s) belongs to.
 - **Include unique sub sites, lists and folders**: Specify if you want to assign permissions to these contents.
- d. Click the **Clone** button.




8. Manage Users and Groups

Permission Manager provides the user and group management, including create, edit and delete SharePoint groups.


8.1 View all SharePoint groups

Permission Manager provides the features to manage SharePoint groups, here will illustrate how to view all SharePoint groups.

- a. Navigate to User and Group Management.
- b. On the farm tree, click the root site of one site collection, and click **SharePoint Groups** node.




c. Select the checkbox before Show all SharePoint groups.







d. And all SharePoint groups will be shown in the table as followings.



e. The number of Members column is a link to the SharePoint group, click the number.



f. Then you will enter the SharePoint group page as following.






8.2 Create SharePoint group

Permission Manager (2.0) allows administrator to create new SharePoint group in site.

- a. Navigate to User and Group Management.
- b. Select one site, and click SharePoint Groups.
- c. Click the **Create Group** button on the toolbar and a dialog window will appear.



In **Name and Description** section, type the group name and description.

In **Owner** section, type a user or SharePoint group name.

In **Members** section, type the user or domain group names which you want to add to this group.

In **Give Group Permission** section, specify the permissions that you want the members have.

d. Then click **Create** to begin the operation.


8.3 Edit SharePoint group

This function enables administrator to modify the SharePoint group properties, include name, description, group owner and permissions.

a. Navigate to User and Group Management.



- b. Select one site, and click **SharePoint Groups**.
- c. Select one SharePoint group, and click the **Edit Group** button on the toolbar and a dialog window will appear.



In Name and Description section, modify the group name and description.

In **Owner** section, type a new user or SharePoint group name.

In **Give Group Permission** section, modify the permissions that you want the members have.


d. Then click **OK** to begin the operation.

8.4 Delete SharePoint group

This feature allows administrator to delete the SharePoint group from the site or site collection.

- a. Navigate to **User and Group Management**.
- b. Select one site, and click **SharePoint Groups**.
- c. Select one or more SharePoint groups, and click the **Delete Group** button on the toolbar and a confirm window will appear.





d. Then click **OK** to delete the SharePoint groups from the site collection.

8.5 Export SharePoint groups

This feature enables administrator to export SharePoint groups and members to an excel file.

- a. Navigate to User and Group Management.
- b. Select one site, and click **SharePoint Groups**.
- c. Click the **Export All Groups** button on the toolbar and a confirm window will appear.




d. Then click **Save** to export the groups and members to excel file.

8.6 Add Users in group

This feature allows administrator to add users or groups in a selected SharePoint group.

- a. Navigate to User and Group Management.
- b. Select one site, and click one SharePoint group.
- c. Click the **Add Users** button on the toolbar and a confirm window will appear.





In **Users/Groups** textbox, type the user or group names.

d. Click **OK** button, then the users or groups will be added in group.

8.7 Copy/Move Users to SharePoint groups


These functions powers administrator to copy or move users from current SharePoint group to others.

- a. Navigate to User and Group Management.
- b. Select one site, and click one SharePoint group.
- c. Select the users or groups which you want to copy/move to other SharePoint groups.



d. Click the **Copy Users to** or **Move Users to** button on the toolbar and a confirm window will appear.






In **Select Groups** section, select the target SharePoint groups. You can select the site first, and select the nested SharePoint groups.

e. Click **OK** button, then the users will be added to those groups.

8.8 Delete group members


This feature allows administrator to delete users from the SharePoint group.

- a. Navigate to User and Group Management.
- b. Select one site, and click one SharePoint group.
- c. Select the users or groups which you want to remove from SharePoint groups.



d. Click the **Remove User from Group** button on the toolbar and a confirm window will appear.






e. Click **OK** button, then the users will be removed from the group.

8.9 Delete users from site collection


Permission Manager allows administrator to delete users from the site collection.

- a. Navigate to User and Group Management.
- b. On the farm tree, select root site of one site collection, and click **All Users** node.
- c. Select the users which you want to delete from the site collection.



d. Click the **Delete Users** button on the toolbar, and a dialog will appear as followings.





e. Confirm and click **OK**. Then users will be deleted from the site collection.

8.10 Export SharePoint users

The application allows administrator to export all site collection users to an excel file for further analysis and audit.

- a. Navigate to User and Group Management.
- b. On the farm tree, select root site of one site collection, and click **All Users** node.
- c. Click **Export All Users** button on the toolbar, and following dialog will appear.




d. Specify the location to save the file.

8.11 Delete domain groups


Permission Manager allows administrator to delete domain groups which have been added in SharePoint.

- a. Navigate to User and Group Management.
- b. On the farm tree, select root site of one site collection, and click **Domain Groups** node.





- c. Select the domain groups which you want to remove from the site collection
- d. Click Delete Group button on the toolbar, and a dialog will appear as followings.




e. Confirm and click OK, then the groups will be deleted.



8.12 View Group members

This feature allows administrator to check the members of one domain group without entering the active directory server.

- a. Navigate to **User and Group Management**.
- b. On the farm tree, select root site of one site collection, and click **Domain Groups** node.
- c. Select the domain groups which you want view the members.
- d. Click **View Group Members** button on the toolbar, and a dialog will appear as followings.



- e. Click **Export**, you can save the members to an excel file.
- f. Or, click **Close** to exit the dialog.

8.13 Export all domain groups

This feature enables administrator to export all domain groups (added in SharePoint) and members to an excel file.

- a. Navigate to User and Group Management.
- b. On the farm tree, select root site of one site collection, and click **Domain Groups** node.
- c. Click **Export All Groups** button on the toolbar, and following dialog will appear.





d. Specify the location to save the file.



9. Manage Column & View Permission

9.1 Manage Column Permission

Permission Manager allows you to manage column permissions for any site or list.


The following steps will show you how to configure column permission settings.

9.1.1 Entering column permission

a. Navigate to **Column/View Permission**.




b. Select one site or list from the farm scope tree and then click **Column Permission**.






c. The **Column Permission** settings are shown as following.




9.1.2 Enable/Disable column permission

You can enable or disable the Column Permission feature for the list and library.

- a. Enter the **Column Permission** settings page for the list or site (see section 6.1.1).
- b. To enable column permission, select **Enable** from the drop-down list.



c. To disable the product, select **Disable** from the drop-down list.




9.1.3 Activate/Deactivate permission part

The Status column displays whether a permission part is Activated or Deactivated.

- a. Enter the **Column Permission** settings page from a list or site.
- b. Select a permission part that you want to activate.
- c. Click Activated or Deactivated.






9.1.4 Add a permission part

A permission part is a container which contains the selected user(s) and columns permissions. To set column permissions on the list or library, you first need to add permission parts.

- a. Enter the **Column Permission** settings page from one list or site.
- b. Click Add Permission Part.



c. In the **Part Name** box enter a name.



d. In the **Include Users** section, specify the user(s) or group(s).




e. In the **Exclude Users** section, enter the user(s) or group(s).



f. In the **Permission Settings** section, select the columns and set as **hidden** or **read-only** for each item form.






g. Click **OK** to add the permission part.

9.1.5 Edit permission part

- a. Enter the **Column Permission** settings page from list or site settings.
- b. Select the permission part which you want to edit by either clicking **Edit** or clicking the permission part name.
- c. Edit the details of this permission part. Then click **OK** to save the settings.

9.1.6 Delete permission part

- a. Enter the **Column Permission** settings page from one list or site.
- b. Select the permission part you want to delete by clicking **Delete**.




Note: Permission parts that have been deleted cannot be restored.

9.1.7 Export/Import permission settings

Export

- a. Enter the Column Permission Settings page.
- b. Click the **Export** button.







- c. A popup window will open.
- d. Select a location and save the settings.

Import

a. Enter the Column Permission settings page and click Import.



b. In the popup window browse for a file and upload it.



- c. Click **OK**.
- d. Or click **Cancel** to abort importing the specified permission settings.




9.1.8 Advanced Settings

The Advanced Settings section lets you decide if read-only columns can be edited on object-model level or by applications that use object-model.

This feature will also control if the read-only columns can be modified in datasheet view.

- a. Enter Column permission settings page.
- b. Click Advanced Settings.



c. To enable modification of the read-only columns, select the check box next to **Allow modification of read-only column**.



9.2 Manage View Permission


9.2.1 Entering view permission

a. Navigate to Column/View Permission.




b. Select a site or list from the farm scope tree and then click **View Permission**.






c. The view permission settings are shown as following.




9.2.2 Enable/Disable view permission

You can enable or disable the **View Permission** feature for the list and library.

- a. Enter the View Permission settings page for the list or site.
- b. To enable view permission, select **Enable** from the drop-down list.



c. To disable the product, select **Disable** from the drop-down list.




9.2.3 Activate/Deactivate permission part

The **Status** column displays whether a permission part is activated or deactivated.

a. Enter the **View Permission** settings page from a list or site.




- b. Select a permission part that you want to activate.
- c. Click Activated or Deactivated.



9.2.4 Add a permission part

A permission part is a container which contains the selected user(s) and view permissions. To set view permissions on the list or library, you first need to add permission parts.

- a. Enter the View Permission settings page from one list or site.
- b. Click Add Permission Part.



c. In the **Part Name** box enter a name.



d. In the **Include Users** section, specify the users or groups.




e. In the **Exclude Users** section enter the users or groups.






f. In the **Permission Settings** section, specify the permissions for each view.



g. In the Set Default View section specify the default views for the included users.



h. Click **OK** to add the permission part.

9.2.5 Edit permission part

- a. Enter the **View Permission** settings page from list or site.
- b. Select the permission part which you want to edit by either clicking **Edit** or clicking the permission part name.
- c. Edit the details of this permission part, and click **OK** to save the settings.

9.2.6 Delete permission part

- a. Enter the **View Permission** settings page on one list or site.
- b. Select the permission part you want to delete by clicking **Delete**.





Note: Permission parts that have been deleted cannot be restored.

9.2.7 Export/Import permission settings

The Export and Import functions are same as for column permission.


9.2.8 Advanced Settings

In the Advanced Settings page, you can configure **Default Settings for View Permission** and **Redirect Page Settings**.


Setting view default permission settings

This function defines the default behavior for View Permissions.

a. In the view permission settings page, click **Advanced Settings**.



b. In the Default Settings for View Permission section, select **Hidden** or **Visible**.



 If the default level is set as **Hidden**, then all existing and new views will be hidden by the View Permission settings unless you specifically set these views as **full access** or **read-only**.



 Setting the default to be Visible will make all existing and new views accessible by default.

Note: You can set permissions for each individual view in the Permission part.

c. Click OK.

Setting the redirect pages

These settings provide the option to configure notifications if views are unavailable to users.


If activated, any users without sufficient permissions will be directed to a page presenting them with the following message.

- a. In **Redirect Page Settings** section, click the check box next to the **Use redirect page**.
- b. Type your message in each of the text boxes.

There are four messages that can be configured. However, each message has a default message preset.

Redirect Page Settings

Configure redirect page settings. If you enable the redirect page settings for this list, any user that attempts to access a view to which he does not have the necessary permissions will automatically be redirected to a page containing the specified text. If the redirect page is not enabled, the user will simply see the default "Access Denied" message or be sent to the next available view.



- The **View unavailable message.** This message will be displayed if the user does not have sufficient permissions to access the view selected.
- The **All views unavailable message**. This message will be displayed if the user does not have sufficient permissions to access any view for this list.
- The "Go to view" button text. This message will be displayed on the Go to view button to direct the user to the next available view.
- The "Return to homepage" button text. This message will be displayed on the Return to homepage button to direct the user from this list.
- c. Click **OK**.




10. Manage Account

Permission Manager allows administrators to configure other domain users as the administrator to manage permissions.

Note: Only the default administrator has permission to manage accounts. Otherwise, you cannot see the Account Management link.

10.1 Add Account


a. Navigate to **Settings** > **Account Management**.



b. Enter a domain user in the text box.




c. Click **Add** so the user can sign in to Permission Manager.




10.2 Delete Account

a. Navigate to **Settings** > **Account Management**.






b. Select the user who you want to remove from the table.



- c. Click Delete.
- d. There will be a message to confirm if you want to delete the user. Click **OK**. The user now cannot sign in to Permission Manager.






11. Logs


Permission Manager records each operation in the logs.

11.1 View details


a. Click **Settings** and then click **Logs**.



b. You will see the following dialog window:




c. Select an item and click **Show details**. A dialog window will appear to show details.





11.2 Delete logs

a. Navigate to **Settings** > **Logs**.



b. Click the **Delete All Logs** button on the toolbar.



Actions	ID	Date and Time	Operator	Details
Clone Permissions	81	12/11/2012 10:34:44 AM	spb2010t0\administrator	Show details
Change Inheritance	79	12/10/2012 6:14:39 PM	spb2010t0\administrator	Show details
Grant Permissions	80	12/10/2012 6:14:39 PM	spb2010t0\administrator	Show details
Clone Permissions	78	12/10/2012 4:58:36 PM	spb2010t0\administrator	Show details
Grant Permissions	77	12/6/2012 7:13:01 PM	spb2010t0\administrator	Show details

c. All the logs will be deleted.

